

Setup Instructions for Wired

Setting Up Your Computer to Connect to ResNet

1. Find the Ethernet port on your computer. It resembles a telephone jack, but is wider.
2. Connect one end of your Ethernet cable to the Ethernet port on your computer.
3. Find the ResNet jack in your room. It will be on a silver wall plate and will have a yellow jack. It will resemble a telephone jack.
4. Connect the other end of your Ethernet cable to the DATA 1 port on your ResNet jack.
5. Configure your computer:
 - a. Windows Vista
 - b. Windows XP
 - c. Mac OS X 10.4 (Tiger)
 - d. Mac OS X 10.5 (Leopard)

Mac OS X 10.4 (Tiger):

Configure:

1. Click on the **Apple menu** and select **System Preferences**. In the **System Preferences** window, select the **Network icon** from the **Internet & Network group**.
2. In the **Network window**, set **Location: to Automatic**, then set **Show: to Built-in Ethernet**, and **Configure IPv4: to Using DHCP**. Click **Apply Now**.

Authenticate:

1. Open a web browser and navigate to a non-UAB website such as www.google.com.
2. You will be prompted to register for UAB ResNet.
 - a. Enter your BlazerID and password.
 - b. Download the Client Security Agent when prompted.
3. When the Client Security Agent is downloaded, run the file. Depending on your system, it may be located on your Desktop or in your Downloads folder.
4. You will receive a notification that your registration is complete. Close and reopen your web browser to confirm your registration.

Mac OS X 10.5 (Leopard):

Configure:

1. Click on the **Apple menu** and select **System Preferences**. In the **System Preferences** window, select the **Network icon** from the

Internet & Network group.

2. In the **Network window**, set **Location: to Automatic**.
3. Select **Ethernet** from the list of connections on the left side of the window.
4. Set **Configure** to **Using DHCP**.
5. Click **Apply** and close the window.

Authenticate:

1. Open a web browser and navigate to a non-UAB website such as www.google.com.
2. You will be prompted to register for UAB ResNet.
 - a. Enter your BlazerID and password.
 - b. Download the Client Security Agent when prompted.
3. When the Client Security Agent is downloaded, run the file. Depending on your system, it may be located on your Desktop or in your Downloads folder.
4. You will receive a notification that your registration is complete. Close and reopen your web browser to confirm your registration.

Windows Vista:

Configure:

1. Click on the **Windows logo** in the lower left corner of your desktop.
2. Click **Control Panel**, and then click **Network and Internet**.
3. In the menu that appears, select **Properties**.
4. Select the **Internet Protocol (TCP/IP)** option and click the **Properties** button. Choose **Obtain IP Address Automatically** and **Obtain DNS Server Address Automatically** options.
5. Click **OK**, then **OK** again.

Authenticate:

1. Open a web browser and navigate to a non-UAB website such as www.google.com. (Note that **MSN.com will not work. Choose a non-Microsoft website.**)
2. You will be prompted to register for UAB ResNet.
 - a. Enter your BlazerID and password.
 - b. Download the Client Security Agent when prompted.
3. When the CSA download begins, choose **Run**.
 - a. Choose **Run** a second time if prompted.
4. Follow the on screen instructions to complete installation of the Client Security Agent.
5. You will be prompted again for your BlazerID and password.
6. Your computer will be scanned.
 - a. If your computer does not meet the software requirements for

ResNet, you will be prompted with actions needed to solve the issue.

- b. If your computer DOES meet the software requirements, you will be notified and you will be connected to ResNet.

Windows XP

Configure:

1. From the **Control Panel**, double-click on the **Network and Internet Connections** or click on **Switch to Classic View** on the left of the screen.
2. Double click on the **Network Connections icon**.
3. Double click on the **Local Area Connection icon** and bring up the **Local Area Connection Status window**. Click on **Properties**.
4. In the **Local Area Connection Properties window**, select the entry for **Internet Protocol (TCP/IP)**, and then click on the **Properties** button.
5. Choose **Obtain an IP Address Automatically** and **Obtain DNS Server Address Automatically** options. Click **OK**.
6. Click **OK** to close the **Local Area Connection Properties window**; click **OK** to close the **Local Area Connection Status window**.

Authenticate:

1. Open a web browser and navigate to a non-UAB website such as www.google.com. (Note that MSN.com will not work. Choose a non-Microsoft website.)
2. You will be prompted to register for UAB ResNet.
 - a. Enter your BlazerID and password.
 - b. Download the Client Security Agent when prompted.
3. When the CSA download begins, choose **Run**.
 - a. Choose **Run** a second time if prompted.
4. Follow the on screen instructions to complete installation of the Client Security Agent.
5. You will be prompted again for your BlazerID and password.
6. Your computer will be scanned.
 - a. If your computer does not meet the software requirements for ResNet, you will be prompted with actions needed to solve the issue.
 - b. If your computer DOES meet the software requirements, you will be notified and you will be connected to ResNet.